



CZ solution

CZ Print Release Station --- Step by Step Configuration

1. Components	2
2. Setup a Printer on Print Release Station to Control Printing.....	3
3. Scenarios.....	8
3.1 CZ Print Release Station Staff-Mode	8
3.2 CZ Print Release Station Staff-Mode with Popup Notification.....	16
3.3 CZ Print Release Station User-Mode with Login and Popup Notification	12
3.4 CZ Print Release Station User-Mode with Self-Payment Equipment	18
3.5 CZ Print Release Station User-Mode with Secure Card Reader Authenticator	18
3.6 CZ Print Release Station User-Mode with Prepaid Account	22
3.7 CZ Print Release Station User-Mode with Windows Active Directory Authentication	22
3.8 CZ Print Release Station User-Mode with Free Print Quotas	22
3.9 Add a Slave Print Release Station	22
4. Use Windows Group Policy to remotely install CZ Popup.....	30
5. Frequently Asked Questions.....	30

1. Components

CZ Print Release Station includes the following components:

Master Print Release Station (Required) Master Print Release Station stores all configurations and holds all print jobs until they are released. It can be installed on any Windows 32-bit or 64-bit computer that has printers shared.

CZ Popup (Optional Add-On) CZ Popup is designed for print job notification, and it must be installed on the workstation. CZ Popup notifies users the print job information including document name, printer name, number of pages and total cost after they send a print job. It also allows users to change their print job name for their privacy, and (or) create a password that they can use to release their print jobs on the print release station, and (or) create a user id for their print jobs that they can use to show only their print jobs on the print release station (for some environments that students use their own laptops to print or environments that user id is not unique). CZ Popup can be installed and run on Windows, Mac OSX / Classic or Linux client computers.


CZ Print Job Report (Optional Add-On) CZ Print Job Report is a Free Software allowing you to generate and view 94 reports including 54 default reports and 40 customized reports, and export these reports to Adobe-PDF, MS-Word, MS-Excel and Rich Text formats. These reports are designed for your print cost analysis. It can be installed on any Windows 32-bit or 64-bit computer.

Slave Print Release Station (Optional Add-On) The Slave Print Release Station can hold all print jobs or some of print jobs on the Master Print Release Station depending on the printer settings. Users can use either Master Print Release Station or Slave Print Release Station to release their print jobs. It can be installed on any Windows 32-bit or 64-bit computer.

CZ Remote Cashier (Optional Add-On) CZ Remote Cashier can be installed on any staff computer to manage prepaid account remotely. It can be installed on any Windows 32-bit or 64-bit computer.

2. Setup a Printer on Print Release Station to Control Printing

Step 1. Download and extract the [30-day trial version](#) of CZ Print Release Station, then double click **czprs-setup.exe** to install Master Print Release Station.




On the computer (e.g. \\PRS) where Master Print Release Station is installed:



Step 2. Click Start --> Settings --> Devices and Printers.

Step 3. Click "Add a printer" button to start the Add Printer Wizard, and then click Next.



Step 4. Click the "Add a local printer or network printer with manual settings" option and then click Next.




Step 5. Select a port, for example Standard TCP/IP Port, Parallel / USB port or LPR Port and follow the instructions on screen. If the port is not in the list, select "Create a new port" to add a new port.



Step 6. The printer icon will be added to your Devices and Printers. Right click the printer icon and click Printer properties, share the printer and uncheck "Render print jobs on client computers".




Step 7. Select "Start printing after last page is spooled" in "Advanced" tab and assign "CREATOR OWNER" only "Print" permission in the "Security" tab.



Step 8. Click Start -> All Programs -> CZ Solution -> CZ Print Release Station - Master to run CZ Print Release Station for the first time. If Preferences window doesn't appear, click menu Print Jobs -> Preferences.

Step 9. Click **Refresh List**, select the printers you want to control in the list of "Available Shared Printers" and click **Add** to add it to the list of "Monitored Printers", click **Save**, and then click **Exit**.




Step 10. On each workstation that you want to control the print jobs, add shared printer \\PRS\HP LaserJet 4:


10.1 Choose Start -> Devices and Printers.

10.2 Click "Add a printer" button to start the Add Printer Wizard, and then click Next.

10.3 Click the "Select a shared printer by name" option and follow the instructions on screen.



10.4. The printer icon will be added to the Devices and Printers. The network printer name is like "**Printer-Name on Print-Release-Station-Computer-Name**".



Step 11. Send a print job from a workstation. The print job is held in CZ Print Release Station -> Waiting Jobs. You can click Print button to release it. There are different ways to release print jobs. Please see [Scenarios](#) for more details.

CZ Print Release Station 7.0.0.36 - Master (Staff Mode)

Print Jobs Document View Help Online Support

Refresh Preview Print Cancel Cancel All Preferences Printer Status Select All Save Help

User	Computer	Description	Pages	Cost	Submitted	Printer	Color	Duplex	Paper Size
gary	catpc	TEST.txt - Notepad	1	0.00	5/9/2016 3:59:12 PM	HP LaserJet 4	No	No	Letter 8 1/2 x 11 in

Print Jobs

- Waiting Jobs
 - gary
- Deleted Jobs
- Printed Jobs

Selected Waiting Jobs Total Pages: 1 Total Cost: 0.00

3. Scenarios

3.1 CZ Print Release Station Staff-Mode

1. A user sends a print job from a workstation.
2. CZ Print Release Station holds the print job with detail print job information.
3. The staff collects the payment and releases the print job for the user. The printing activity is recorded in the database of CZ Print Release Station.

Note: All unclaimed waiting jobs can be deleted automatically at the defined time in Preferences --> Print Jobs.

Note: The Waiting Jobs can be showed either by workstation name or user name. This can be set in “Preferences --> Print Jobs”.

CZ Print Release Station 7.0.0.36 - Master (Staff Mode)

Print Jobs Document View Help Online Support

Refresh Preview Print Cancel Cancel All Preferences Printer Status Select All Save H

Print Jobs	User	Computer	Description	Pages	Cost	Submitted	Printer	Color	Duplex	Paper Size
Waiting Jobs	Nancy	Station3	Report - Notepad	16	1.60	7/16/2006 8:49:28 PM	Brother HL-5070N BR...	No	No	Letter 8 1/2 x 11
Gary	Gary	Station2	Microsoft Word - ...	3	0.30	7/16/2006 8:47:01 PM	LAB_HPLaserJ5M	No	No	Letter 8 1/2 x 11
Nancy	Peter	Station5	Homework 1	5	0.50	7/16/2006 8:53:23 PM	LAB_HPLaserJ5M	No	No	Letter 8 1/2 x 11
Peter										
Tom										
Deleted Jobs										
Printed Jobs										

Selected Waiting Jobs Total Pages: 1 Total Cost: 0.10

CZ Print Release Station 7.0.0.36 - Master (Staff Mode)

Print Jobs Document View Help Online Support

Refresh Preview Print Cancel Cancel All Preferences Printer Status Select All Save H


Print Jobs	User	Computer	Description	Pages	Cost	Submitted	Printer	Color	Duplex	Paper Size
Waiting Jobs	Nancy	Station3	Report - Notepad	16	1.60	7/16/2006 8:49:28 PM	Brother HL-5070N BR...	No	No	Letter 8 1/2 x 11
Station2	Gary	Station2	Microsoft Word - ...	3	0.30	7/16/2006 8:47:01 PM	LAB_HPLaserJ5M	No	No	Letter 8 1/2 x 11
Station3	Peter	Station5	Homework 1	5	0.50	7/16/2006 8:53:23 PM	LAB_HPLaserJ5M	No	No	Letter 8 1/2 x 11
Station4										
Station5										
Deleted Jobs										
Printed Jobs										

Selected Waiting Jobs Total Pages: 1 Total Cost: 0.10


Note: If the [Master – Slave infrastructure](#) is used, the print job can be listed on both the Master Print Release Station and the Slave Print Release Station and staff can use either one to release the print jobs.

3.2 CZ Print Release Station Staff-Mode with Popup Notification


Step 1. In Preferences --> User Mode, select “Show popup notification when a print job is submitted on the workstation”.



Step 2. Copy "setup.exe" to each workstation, double click "setup.exe" to install the popup. The add-on CZ Popup can also be installed silently and remotely using [Windows Group Policy](#).



Step 4. Click Start -> All Programs -> CZ Solution -> CZ Popup to run the popup. Enter the computer name or the IP Address of the computer that has Master Print Release Station - installed.




Note:

1. CZ Popup will be started automatically when user login next time.
2. Modify Silent_Installation\CZ Popup.msi package to include the name or IP address of the computer where you installed Master Print Release Station, so you don't have to enter it manually when you run CZ Print Job Agent the first time on each workstation. Visit [Step 1 of Windows Group Policy](#) how to use **Orca** to modify **CZ Popup.msi** .

Scenario

1. A user sends a print job from a workstation.
2. A popup window appears on the workstation (Windows, Mac OSX / Classic, or Linux client computer) showing the document name, printer name, total number of pages, and cost.




If the popup doesn't appear, see [FAQ 3](#).

3. The staff collects the payment and releases the print job for the user. The printing activity is tracked and saved in the database.


Note: If the [Master – Slave infrastructure](#) is used, the print job can be listed on both the Master Print Release Station and the Slave Print Release Station and staff can use either one to release the print jobs. Check 3.9 Add a Slave Print Release Station.

3.3 CZ Print Release Station User-Mode with Login and Popup Notification


Step 1. In Preferences --> User Mode, select “Allow users to enter user id or computer name to show only their print jobs” and “Show popup notification when a print job is submitted on the workstation”.




Step 2. In Menu Print Jobs, click "Switch to User Mode". You can switch back to Staff Mode by pressing "Alt" and "a" keys together, and then enter the password defined in Preferences --> User Mode.



Step 3. Copy "setup.exe" to the workstation, double click "setup.exe" to install the popup. The add-on CZ Popup can also be installed silently and remotely using [Windows Group Policy](#).



Step 4. After the installation completes, launch CZ Popup or click Start -> All Programs -> CZ Solution -> CZ Popup to run the popup. Enter the computer name or the IP Address of the computer that has Master Print Release Station - installed.




Note:

1. CZ Popup will be started automatically when user login next time.
2. Modify Silent_Installation\CZ Popup.msi package to include the name or IP address of the computer where you installed Master Print Release Station, so you don't have to enter it manually when you run CZ Print Job Agent the first time on each workstation. Visit [Step 1 of Windows Group Policy](#) how to use **Orca** to modify **CZ Popup.msi** .

Scenario

1. A user sends a print job from a workstation.

2. A popup window appears on the workstation (Windows, Mac OSX / Classic, or Linux client computer) showing the document name, printer name, total number of pages, and cost.




If the popup doesn't appear, see [FAQ 3](#).


Note: The users are allowed to

- (i) Change their print job names for the privacy, and (or)
- (ii) Create a password that they can use to release their print jobs on the print release station, and (or)
- (iii) Create a user id for their print jobs that they can use to show only their print jobs on the print release station (for some environments that users are allowed to use their own laptops to print or environments that user id is not unique).


The options "Require user to change the document name", "Require user to set password for the print job" and "Require user to set user id" can be selected in Preferences --> User Mode.



3. CZ Print Release Station holds the print job with detail print job information, but the job is not showed on the screen
4. The user goes to the Print Release Station and types the login id or workstation name to show only his / her print job.



5. The user either releases or deletes the print job. The printing activity is recorded in the database of CZ Print Release Station.




Note: The user needs to enter the password to release or delete the print job if the password on the Pop up is enabled in step 2.

6. The user clicks the exit button to return the login window or the Print Release Station can return to login window automatically after 30 seconds of idle time.


Note: If the [Master – Slave infrastructure](#) is used, the print job can be listed on both the Master Print Release Station and the Slave Print Release Station and users can use either one to release the print jobs.

3.4 CZ Print Release Station User-Mode with Self-Payment Equipment

Step 1. In Preferences --> User Mode, select "Use self payment equipment".



Step 2. In Menu Print Jobs, click "Switch to User Mode". You can switch back to Staff Mode by pressing "Alt" and "a" keys together, and then enter the password defined in Preferences --> User Mode.



Scenario


1. A user sends a print job from a workstation.
2. CZ Print Release Station holds the print job with detail print job information.
3. The user goes to the Print Release Station and makes payment using coins, bill, cash card or credit card to release the print job.




Note: If the [Master – Slave infrastructure](#) is used, the print job can be listed on both the Master Print Release Station and the Slave Print Release Station and users can use either one to release the print jobs.

3.5 CZ Print Release Station User-Mode with Secure Card Reader Authenticator

Step 1. In Preferences --> User Mode, select “Use card containing xxxxx to release the print job”.




Step 2. In Menu Print Jobs, click "Switch to User Mode". You can switch back to Staff Mode by pressing "Alt" and "a" keys together, and then enter the password defined in Preferences --> User Mode.



Scenario

- 1. A user sends a print job from a workstation.
- 2. CZ Print Release Station holds the print job with detail print job information.
- 3. The user clicks the Print button.
- 4. A popup "Please swipe / insert your card" appears.




- 5. The user swipes or inserts the card to release the print job.


Note: If the [Master – Slave infrastructure](#) is used, the print job can be listed on both the Master Print Release Station and the Slave Print Release Station and users can use either one to release the print jobs.

3.6 CZ Print Release Station User-Mode with Prepaid Account

Step 1. In Preferences --> User Mode, select "Use prepaid account and pin to release the print job".




Step 2. In Preferences --> Prepaid Accounts", click "Add" button to add a new account. The user account can also be imported from Windows Active Directory or a CSV file (You can export the users to CSV file, add / update that CSV file, then import it back). If the cost of each page is 0.10 in Preferences --> Printers, then balance 1.00 means the user can print 10 pages.




Note:

CZ Print Release Station has addon CZ Remote Cashier that can be installed on any staff computer to manage prepaid account remotely. The remote cashier account can be created in CZ Print Release Station Preferences -> Print Jobs.




Step 3. In Menu Print Jobs, click "Switch to User Mode". You can switch back to Staff Mode by pressing "Alt" and "a" keys together, and then enter the password defined in Preferences --> User Mode.



Scenario


1. A user sends a print job from a workstation.
2. CZ Print Release Station holds the print job with detail print job information.
3. The user goes to the Print Release Station and types the prepaid account and pin to release the print job. The job can't be printed out if there is not enough balance left for that user.




Note: If the [Master – Slave infrastructure](#) is used, the print job can be listed on both the Master Print Release Station and the Slave Print Release Station and users can use either one to release the print jobs.

3.7 CZ Print Release Station User-Mode with Windows Active Directory Authentication

Step 1. In Preferences --> User Mode, select T “Use Windows Active Directory User Name and Password to release the print job”.




Step 2. In Menu Print Jobs, click "Switch to User Mode". You can switch back to Staff Mode by pressing "Alt" and "a" keys together, and then enter the password defined in Preferences --> User Mode.




3.8 CZ Print Release Station User-Mode with Free Print Quotas

Step 1. In Preferences --> Print Jobs, select either "Free printing for the first ## pages per day per person" or "Free printing for the first ## pages per term per person". In Preferences --> User Mode, select "Lock the desktop in user mode" to lock Print Release Station computer in user mode and select "Auto switch to user mode when starting the application" to switch to user mode automatically when Print Release Station starts.



Step 2. In Menu Print Jobs, click "Switch to User Mode". You can switch back to Staff Mode by pressing "Alt" and "a" keys together, then enter the password defined in Preferences --> User Mode.



3.9 Add a Slave Print Release Station

Step 1. On Master Print Release Station, go to Preferences -> Print Jobs, select "Enable add-on slave print release station", click Save, and then click Exit.



Note:

Master Print Release Station can be run as Windows service on your current print server regardless of whether someone is logged on.

1.1. Exit Master Print Release Station if it is running.

1.2. Rename file C:\Program Files\CZ Solution\CZ Print Release Station\config\noservice to a different name.


1.3. Start CZ Print Release Station and select the menu item "Tools-->Install CZ Print Release Station (Master) Service".

1.4. Restart the computer. When the Master Print Release Station service is running, the process "PrintSaverSetup.exe" is running in Task Manager.

If the Master Print Release Station is used by staff or users to release the print jobs, **don't install CZ Print Release Station (Master) Service.**

Step 2. On a computer that will be Slave Print Release Station


2.1 Double click **CZ Print Release Station_Slave.msi** to install Slave Print Release Station.




2.2 Choose Start -> Devices and Printers.

2.3 Click "Add a printer" button to start the Add Printer Wizard, and then click Next.


2.4 Click the "A network printer" option and follow the instructions on screen.



2.5 The printer icon will be added to the Printers and Faxes folder (or Devices and Printers folder). The network printer name is like "Printer-Name on Print-Server-Name".



2.6 Select menu Print Jobs --> Preferences, enter the IP address or computer name of print server where Master Print Release Station is installed, then click "Connect" and "Get Settings" button.



Step 3. Send a print job from a workstation to the network printer (For exmaple \\PRS\HP LaserJet 4). The print job is held on both Master Print Release Station and Slave Print Release Station. You can click Print button to release it from either Master Print Release Station or Slave Print Release Station.

The screenshot shows the Master interface of the CZ Print Release Station. The window title is "CZ Print Release Station 7.0.0.36 - Master (Staff Mode)". The menu bar includes "Print Jobs", "Document", "View", "Help", and "Online Support". The toolbar contains icons for Refresh, Preview, Print, Cancel, Cancel All, Preferences, Printer Status, Select All, Save, and Help. On the left, a tree view shows "Print Jobs" with sub-items: "Waiting Jobs" (highlighted), "Deleted Jobs", and "Printed Jobs". The main area is a table with the following data:

User	Computer	Description	Pages	Cost	Submitted	Printer	Color	Duplex	Paper Size
gary	catpc	TEST.txt - Notepad	1	0.00	5/9/2016 3:59:12 PM	HP LaserJet 4	No	No	Letter 8 1/2 x 11 in

At the bottom, a summary bar shows "Selected Waiting Jobs", "Total Pages: 1", and "Total Cost: 0.00".

The screenshot shows the Slave interface of the CZ Print Release Station. The window title is "CZ Print Release Station 7.0.0.36 - Slave (Staff Mode)". The menu bar and toolbar are identical to the Master interface. The tree view on the left is also identical. The main table shows the same print job, but the printer name is different:

User	Computer	Description	Pages	Cost	Submitted	Printer	Color	Duplex	Paper Size
gary	catpc	TEST.txt - Notepad	1	0.00	5/9/2016 3:59:12 PM	\\PRS\HP Lase	No	No	Letter 8 1/2 x 11 in

At the bottom, a summary bar shows "Selected Waiting Jobs", "Total Pages: 1", and "Total Cost: 0.00".

4. Use Windows Group Policy to remotely install CZ Popup

<http://www.czsolution.com/popupsilentinstall.htm>

5. Frequently Asked Questions

http://www.czsolution.com/prs_faq.htm