

# User manual

(RTSP Server)

*Happytimesoft Technology Co., LTD*

## Declaration

All rights reserved. No part of this publication may be excerpted, reproduced, translated, annotated or edited, in any form or by any means, without the prior written permission of the copyright owner.

Since the product version upgrade or other reasons, this manual will subsequently be updated. Unless otherwise agreed, this manual only as a guide, this manual all statements, information, recommendations do not constitute any express or implied warranties.

---

[www.happytimesoft.com](http://www.happytimesoft.com)



---

## Table of Contents

<b>Chapter 1 Configuration.....</b>	<b>4</b>
1.1 Configuration Templates.....	4
1.2 Configuring Node Description.....	4
<b>Chapter 2 Run RTSP Server.....</b>	<b>7</b>

---

## Chapter 1 Configuration

### 1.1 Configuration Templates

```
<?xml version="1.0" encoding="utf-8"?>
<config>
    <serverip></serverip>
    <serverport>554</serverport>
    <output>
        <url>screenlive</url>
        <video>
            <codec>H264</codec>
            <width></width>
            <height></height>
            <framerate></framerate>
        </video>
        </output>
        <output>
            <url></url>
            <video>
                <codec>H264</codec>
                <width></width>
                <height></height>
                <framerate></framerate>
            </video>
            <audio>
                <codec>AAC</codec>
                <samplerate></samplerate>
                <channels></channels>
            </audio>
        </output>
    </config>
```

### 1.2 Configuring Node Description

<serverip>

Specify the IP address RTSP server bindings, if not specified, the RTSP server will bind to the default routing interface IP address.

---

**<serverport>**

Specify the port RTSP server binding, the default is 554.

**<output>** : Specify the audio and video output parameters, it can configure multiple nodes

**<url>**

Match URL address, it can be filename, or file extension name. Such as:

screenlive : match live screen stream

videodevice : match camera video stream

\*.mp4 : match all mp4 media file

sample.flv : match sample.flv file

If not config this node, it will match all url as the audio/video default output parameters.

The match order from top to bottom, therefore the default output configuration should be placed in the last.

**<video>** : Specify the video output parameters

**<codec>**

Specify the video stream codec, it can specify the following value:

**H264** : output H264 video stream

**MP4**: output MP4 video stream

**JPEG**: output MJPEG video stream

**<width>**

Specify the output video width, If 0 use the original video width (live screen stream use the screen width, camera stream use the default width)

**<height>**

Specify the output video height, If 0 use the original video height (live screen stream use the screen height, camera stream use the default height)

**<framerate>**

Specify the output video framerate, If 0 use the original video framerate (live screen use the default value 15, camera stream use the default value 25)

**<audio>** : Specify the audio output parameters

**<codec>**

Specify the audio stream codec, it can specify the following value:

G711A: output G711 a-law audio stream

G711U: output G711 mu-law audio stream

G726: output G726 audio stream

AAC: output AAC audio stream

---

#### <samplerate>

Specify the audio sample rate, it can specify the following values:

8000, 11025, 12000, 16000, 22050, 24000, 32000, 44100, 48000

If 0 use the original audio sample rate (audio device stream use the default value 8000)

#### <channels>

Specify the audio channel number, 1 is mono, 2 is stereo

If 0 use the original audio channel number (audio device stream use the default value 2)

**Note : G726 only support mono.**

---

## Chapter 2 Run RTSP Server

The server is a console application. To run the server, simply type "rtspserver".

**Note :** The demo version has the following limitations

Maximum support two simultaneous client connections.

Open our website when client connecting.

Only support output H264 video stream

Only support output G711 a-law audio stream

The release version maximum support 64 simultaneous client connections, without any other limitations.