

Demo version has restrictions:

Copied orders with 0.1 lots volume only

Two slave terminals only


Two brokerage companies only: AlpariUK demo and AlpariUS Demo

Full version does not have these limitations.


“PowerTradeCopier” MultiTerminal Installation

The software is easily installed using Setup. The procedure is the same for all versions of this software.


1. Run InstalCopy_rez.exe file (double-click the file named Run InstalCopy_rez.exe). The following screen will appear.





2. Click **Next** to continue the install or *Cancel* to exit. The following screen will appear.




3. Click **Registration**.
4. Click **Next** when the End User License Agreement appears (shown below) or *Cancel* to exit.



5. A "**Destination Folder**" screen will be displayed (shown below). By default the destination folder is set to "C:\Program Files\CopyToolNet". Click the **[Browse]** button to select a different installation Destination Folder. After confirming the Destination Folder, click the **Next** button to start the installation process. You can click the *Cancel* button to exit.



6. The installation process is quick. Upon successful completion of the installation, an installation successful screen will be displayed (shown below). Click the **Exit** button.



7. The shortcut will be created on your desktop and Main Menu.



Important information for “provider” mode.


After installation on master side, your software will be automatically registered as a master. You can send installer for your clients and they can install software on their sides. The second and subsequent installations will be recorded as slaves. Master settings are inactive on slave side. You can add / remove/block/unblock slave accounts on master side.

Your clients can put trader password and adjust copying parameters according their needs on slave side. (master can live field “password” for slave account empty). For “trader mode” master should know trader passwords for slave accounts.


“PowerTradeCopier” MultiTerminal Usage

Master Account

How to add master account? Run MetaTrader Multiterminal "PowerTradeCopier" and press "Setting". Press "Add" button and select server for master account from servers list, put account number in to the User field and investor password. Press "save" button.




If you have not found your sever in our servers list, provide us with information about your server (format ip:port, or *.srv file from Metatrader/config/ folder) and we will add your server immediately. Fill free to contact us for assistance.



Slave Account

How to add slave (sub) accounts? Press "Slaves". Press "Add" button and select server for slave account from server's list, put account number in to the User field and trader password. Press "save" button. You can put information about sub account in to the "Comment" field or live it empty.

Important information for "provider mode". Master should put slave's account number in to the "Login" field and select server. Slave will enter password and adjust copying parameters on slave side according their needs. For "trader mode", all settings are performed on master side.



Slave accounts settings

1. Transmission parameters

1.1. Compliance (mapping)


If your broker have standard quotes symbols (for example: eurUSD, gbpUSD, etc.) , you can skip this point. If your broker have non standard symbols (symbols with prefix or suffix), you should enter prefix or suffix in to the appropriate field.

Example: Broker Forex.com UK Quotes symbols with suffix FXF

Market Watch: 19:58:31

Symbol	Bid	Ask
AUDCADFXF	0.9704	0.9709
AUDJPYFXF	81.20	81.26
AUDNZDFXF	1.2597	1.2606
AUDUSDFXF	0.9163	0.9166
CADJPYFXF	83.65	83.70
CHFJPYFXF	85.86	85.90
EURAUDFXF	1.5979	1.5985
EURCADFXF	1.5511	1.5517
EURCHFXXF	1.5117	1.5120


We should enter suffix FXF in to the “End” field.




1.2. Transformation

Lot section specifies the way of lot calculation on slave side. You can use 3 type of lot calculation:

Ratio(MS), Fixed, Balance.



1.2.1. Ratio(MS)



Slave lot calculated as master lot multiplied by MS.LotRatio.

Sample:


1) $MasterLot = 0.1, MS.LotRatio = 1.0 \Rightarrow SlaveLot = 0.1 * 1.0 = 0.1$

2) $MasterLot = 1.0, MS.LotRatio = 2.0 \Rightarrow SlaveLot = 1.0 * 2.0 = 2.0$

3) $MasterLot = 6.0, MS.LotRatio = 0.5 \Rightarrow SlaveLot = 6.0 * 0.5 = 3.0$

1.2.2. Fixed Lot

Slave lot is equal to "Fixed"



Sample:

1) $MasterLot = 0.1, Fixed = 1.0 \Rightarrow SlaveLot = 1.0$

2) $MasterLot = 1.0, Fixed = 1.0 \Rightarrow SlaveLot = 1.0$

3) $MasterLot = 6.0$, $Fixed = 0.1 \Rightarrow SlaveLot = 0.1$

1.2.3. Balance

<input checked="" type="radio"/> Balance	Pcnt	<input type="text" value="10.00"/>	Basis	<input type="text" value="1000.0"/>
--	------	------------------------------------	-------	-------------------------------------

Slave lot calculated as $AccountBalance() / BP.BalanceBasis * BP.BalancePcnt / 100$.

Sample:

1) $BP.BalanceBasis = 1\,000.0$, $BP.BalancePcnt = 10.0$, current $AccountBalance = 12\,000.0$

$Lot = 12000.0 / 1000.0 * 10.0 / 100 = 1.2$

2) $BP.BalanceBasis = 500.0$, $BP.BalancePcnt = 5.0$, current $AccountBalance = 5\,000.0$

$Lot = 5000.0 / 500.0 * 5.0 / 100 = 0.5$

Lot types: *Equity*, *FreeMargin* and *LotRatio(MRT)* are temporary unavailable.

<input type="radio"/> Equity	Pcnt	<input type="text" value="15.00"/>	Basis	<input type="text" value="1000.0"/>
<input type="radio"/> FreeMargin	Pcnt	<input type="text" value="20.00"/>	Basis	<input type="text" value="1000.0"/>
<input type="radio"/> LotRatio (MRT)	Ratio(MRT)	<input type="text" value="0.00"/>		

1.3. Copying

Edit | Transmission parameters | Order | Pairs | Log
 Compliance | Transformation | **Copying** | Filter | Log
 MinLot: 0.00 | MaxLot: 0.00 | LotDigits: -1
☐ OverwriteStopLoss ☐ OverwriteTakeProfit
 StopLossCopyMode: ☒ A ☐ P TakeProfitCopyMode: ☒ A ☐ P
 NewStopLoss: 200 NewTakeProfit: 200
☐ OverwriteComment NewComment:
 RepeatCount: 5 SlipPage: 10
☒ CopyClose

MinLot and MaxLot You can set minimal and maximal size of lot calculated on slave account.

LotDigits - The allowable number of decimal places in Lot.

MinLot: 0.00 MaxLot: 0.00 LotDigits: -1

You can set copying mode for StopLoss and TakeProfit

"A": absolute mode. StopLoss and TakeProfit values will be copied from master side as is.

"P": pips mode. StopLoss and TakeProfit values will be adjusted.

(1) absolute values transformed to pips,

(2) pips applied to calculate new sl and tp on slave side.

Sample1:

StopLossCopyMode = TakeProfitCopyMode = "A"

Let we have Master Buy order with open price = 1.2000, sl = 1.1900, tp = 1.2100.

Let the open price on Slave terminal is 1.2010.

StopLoss and TakeProfit will be copied as is because copy mode ="A".

Master Buy => Slave Buy

open price 1.2000 => 1.2010

stop loss 1.1900 => 1.1900

take profit 1.2100 => 1.2100

Sample2:

StopLossCopyMode = TakeProfitCopyMode = "P"

Let we have Master Buy order with open price = 1.2000, sl = 1.1900, tp = 1.2100.

Let the open price on Slave terminal is 1.2010.

StopLoss and TakeProfit values will be transformed because copy mode ="P".

Master Buy => Slave Buy


open price 1.2000 => 1.2010

stop loss 1.1900 => 1.1910 (1.2010 - 100 pips)

take profit 1.2100 => 1.2110 (1.2010 + 100 pips)

You can overwrite copying size of stoploss or(and) takeprofit

Also, you can delete or overwrite comments or write new comments.




Also on this tab are two important parameters are set up:

RepeatCount – number of repeats for order copying.


Slippage - difference between the price a trader expects to be filled at, and the price they are actually filled at.

For example if a trader sends a market order in to fill at 10.00 but is only filled at 10.50 - the order was slipped half a point. Such slippage leads to a higher than expected transaction costs. Slippage in equities and futures usually leads traders to use special orders to be more certain of expected costs.



1.4. Filter

Checks minimal and maximal price difference between open price on master side and market price on slave side. CheckMinMaxPriceDiff parameters define Buy zone for Buy orders and Sell zone for Sell orders in units of pips. So this feature makes it possible to open an order at better price.



Sample1:

Master Buy => Slave Buy CheckMinMaxPriceDiff StopLoss side = 50 pips

open price 1.45328 => 1.44828 (1.45328 -50 pips)

Sample2:

Master Buy => Slave Buy CheckMinMaxPriceDiff TakeProfit side = 50 pips

open price 1.45328 => 1.45828 (1.45328 +50 pips)

And vice versa for SELL

Sample3:

Master Sell => Slave Sell CheckMinMaxPriceDiff StopLoss side = 50 pips

open price 1.45328 => 1.45828 (1.45328 +50 pips)

Sample4:

Master Sell => Slave Sell CheckMinMaxPriceDiff TakeProfit side = 50 pips

open price 1.45328 => 1.44828 (1.45328 - 50 pips)



1.5. Log


LogMasterTrades - Log information about open trades from master side.

LogMasterHistoryTrades - Log information about closed trades and cancelled orders from master side.


LogSymbolNotFound - If a copied symbol not found in the market watch window on slave terminal then a warning will be added to the log.

LogOrderAlreadyCopied - Log information in case an order already copied and closed but CopyTool trying to open this order second time.

LogMinMaxPriceDiff - Log information on MinMaxPriceDiff filter triggered.



You can check log for slave terminals and for master terminal.



F.A.Q

General questions

Q. Do I need to run metatrader slave terminals (sub-terminals)

A. No you do not need to run. You need to run just Master terminal and our software "PowerTradeCopier"

Q. Can I copy trades from master terminal with "read only" password

A. Yes, you can copy trades from master terminal with read only "investor" password

Q. Do I need to know my client's account numbers and passwords

A. If you use provider mode, you need to know account numbers only. Your clients can put passwords themselves on slave side. But if you use copier mode you should put traderst passwords on your side.

Q. How big is the delay in copying?

A. Our tool works without delay, but there is a metatrader server's delay for order sending , similar with Metatrader delay.

Installation F.A.Q.

Q. When starting the program I get an error "IP was not found".

A. Please, try to switch off your firewall software or add our application to allowed application list.

Master settings F.A.Q.

Q. I have added master account, but message "Password error" is appear.

A. Please, check your password and your server.

Q. I've not found my server in the servers list.

A. Please, contact us and we will add your server immediately.

Q. I have added master account, but message "Communication error" is appear.

A. Try to restart software. Our toll will rescan servers when started.

Slave settings F.A.Q.

Q. I have added slave account, but message "Password error" is appear.

A. Please, check your password and your server.

Q. I've not found my server in the servers list.

A. Please, contact us and we will add your server immediately.

Q. I have added slave account, but message "Communication error" is appear.

A. Try to restart software. Our toll will rescan servers when started.

Q. Master took trade but my slave account did not take a trade.

A. Please, check log file for possible errors. Most likely causes:

- Requote
- Invalid lot size
- Answer time delay
- Invalid S\L or T\P
- unacceptable price (SL or(and) TP close to the price)
- off quotes
- prohibited(Hedge)
- no money
- not enough money
- Invalid S\L or T\P(2)
- Prohibited by FIFO rule

Q. Will be copied orders that were open before the Multiterminal was running?

A. You can open orders list, select orders and copy or refuse them.

Q. Orders on master account have comments. Can I delete them?

A. Yes, you can. You can delete or rewrite: comments, take profit, stop loss.

Q.EURUSD Sell order was opened on master account . Price 1.3426 Can I copy this order when price will be 1.3430 and gain additional 4 pips?

A. Yes, surer. You can use "Filters" You should set CheckMinMaxPriceDiff StopLoss side = 4 pips. If price grow to 1.3430, order will be copied to slave (price: 1.3430) If no, order will be not copied. Read more about Filters...

Q. Master trade with lot size = 1 standard lot. Can I copy orders on slave with Lot = percent by account balance if my leverage 1:500

A. Yes, you can. Please, read more about Transformation....

©BJF Trading Group inc.

Web: <http://multiterminal.net>

e-mail: support@multiterminal.net

icq: 912-444

skype: borisfes

Risk Warning

Before deciding to participate in the Forex market, you should carefully consider your investment objectives, level of experience and risk appetite. Most importantly, do not invest money you cannot afford to lose. There is considerable exposure to risk in any off-exchange foreign exchange transaction, including, but not limited to, leverage, creditworthiness, limited regulatory protection and market volatility that may substantially affect the price, or liquidity of a currency or currency pair.

