


User Guide

Revised in April, 2016



AccessPatrol

Version 5.0.6

Endpoint Security Tool

AccessPatrol User Guide - Table of Contents

1.0 Introduction to AccessPatrol	4
1.1 CurrentWare Components	5
1.2 System Requirements	6
1.3 Installing the CurrentWare Server, Console and Solutions	7
1.4 Installing the CurrentWare Clients	8
1.4.1 Local CurrentWare Client Install	8
1.4.2 Remote Client Install	9
1.4.3 Deploy CurrentWare Client by Command Line	11
1.4.4 Deploy CurrentWare Client with a Third-Party Software Delivery Tool or Active Directory	11
1.5 Upgrading the CurrentWare Clients	12
1.5.1 Automatic Upgrade of the CurrentWare Clients	12
1.5.2 Manual Upgrade of the CurrentWare Clients	13
1.6 Standalone Installation	13
1.6.1 Installing the CurrentWare Console, Server and Solution	13
1.6.2 Installing the CurrentWare Client	13
1.6.3 Password Protect the CurrentWare Console	13
2.0 CurrentWare Console Overview	14
2.1 Client and Group Management	15
2.2 Redirect Clients	16
2.3 Client Settings	17
2.4 Troubleshooting	18
2.5 Operators	20
2.6 Import Users	21
2.7 Database Backup Scheduler	23
2.8 Auto Delete URL Scheduler	24
2.9 Options	25
2.10 Log Out	26
3.0 Overview of AccessPatrol Functions	28
4.0 Controlling Device Access	29
4.1 Access Permissions	29
4.2 Device Scheduler	30
4.3 Allowed List	31
5.0 Device Reports	33
5.1 Device Report Options	33
5.1.1 Reporting Type	33

5.1.2 Select Mode	33
5.1.3 Reporting Period	33
6.0 Email Reports	35
6.1 Email Settings	36
7.0 AccessPatrol Client Settings	37
8.0 CurrentWare Server Manager	38
8.1 Changing the CurrentWare Client and Console Port	38
8.2 Stopping the CurrentWare Server Service	39
8.3 Compress the CurrentWare Database	39
8.4 Archive and Restore the CurrentWare Database	40
9.0 Licensing	41
9.1 Register your Permanent License key	41
9.2 License Management	42
10.0 Uninstall CurrentWare Server, Console and Solutions	43
10.1 Uninstalling the CurrentWare Solutions	43
10.2 Uninstalling the CurrentWare Server and Console	43
11.0 Uninstall CurrentWare Client	44
11.1 Uninstall CurrentWare Client from the Console	44
11.2 Uninstall CurrentWare Client on the workstation by command line	45
11.3 Uninstall CurrentWare Client on the workstation from the Client Configuration Window	45
12.0 Technical Support	46
13.0 Contacts	47
USA	47
CANADA	47
EUROPE	47
ASIA	47
OTHER COUNTRIES	47

1.0 Introduction to AccessPatrol

AccessPatrol is endpoint security software used for controlling the access of external devices on your network computers

AccessPatrol Device Security

With the influx of portable storage devices and removable media, data theft is becoming an increasing threat to organizations. Devices such as USB sticks, mobile phones, tablets, media players and external hard drives connect seamlessly to company networks, without IT administrators having any knowledge that their company data is being exposed.

Portable devices also provide an easy entryway for infecting systems with viruses or malicious software, thus compromising an organization's network.

Banning these devices in the workplace/schools is becoming increasingly difficult to monitor. As a result, more and more companies are resorting to tools that can prevent users from implementing these devices to their workstations.

CurrentWare's endpoint security solution, AccessPatrol, provides a comprehensive solution for securing company devices to minimize unauthorized access to proprietary information.

1.1 CurrentWare Components

There are four primary components in the CurrentWare Console

CurrentWare Server

This component includes a server Service and database. It houses all the data for the configuration and settings. The CurrentWare Server is the central hub for the CurrentWare Consoles and the CurrentWare Clients to connect to. A Firebird database is used for the data storage.

CurrentWare Console

This component is the management console that the administrator uses to control the functionalities of the CurrentWare Solutions. The administrator will be able to see the connection status of their CurrentWare Clients within the CurrentWare Console.

Multiple consoles can be installed on the same network. Multiple authentications can be assigned to different users to allow or restrict the full functionality of the console.

Note: the CurrentWare Server and the Console components are commonly installed on the same computer. Additional CurrentWare Consoles may be installed on other administrators' computers.

CurrentWare Solutions

This component contains different functionalities based on the solution that you are installing. After the installation of a CurrentWare solution, the solution's functions will be embedded on the right hand side of the CurrentWare Console.

- **BrowseControl:** Web Filtering
- **BrowseReporter:** Internet Tracking and Reporting
- **AccessPatrol:** Endpoint Device Security
- **enPowerManager:** Power Management

CurrentWare Client

This component is to be installed on all computers that need to be managed by the CurrentWare Console. The CurrentWare Clients establish communication to the CurrentWare Server. The client is password protected and runs in stealth mode.

1.2 System Requirements

Hardware Requirement

All components of the CurrentWare Console are supported on desktop computers and server computers with the following specifications.

- **Processor:** any CPU running i3 or similar or faster
- **Memory:** At least 4GB of RAM
- **Disk Space:** At least 500MB of disk space

Software Requirement

All components of the CurrentWare Console are compatible with the following Operating Systems running 32-bit or 64-bit platform

- **Windows XP Professional**
- **Windows Vista Professional**
- **Windows 7 Professional and Ultimate**
- **Windows 8 and 8.1 Professional and Ultimate**
- **Windows 10 Pro and Enterprise**
- **Windows Server 2003, 2008, 2012**

1.3 Installing the CurrentWare Server, Console and Solutions

Follow the instructions below to install the CurrentWare Server, Console and Solutions.

Before you begin your installation:

- Installation of all components must be done with an admin user account.
- The Server and Console components may be installed on the same computer.

1. Download the Setup Files

Download the CurrentWare setup files from our website:

<http://www.CurrentWare.com>

2. Select a Computer to install the CurrentWare Server and Console

3. Install the CurrentWare Server and Console

1. Unzip the setup file that you downloaded from our website and run the **currentware.exe** to initiate the CurrentWare Console Installation Wizard.
2. Proceed to accept the **License Agreement**.
3. Put in your **User Information** (Full Name and Organization name) and select the software usage for “Anyone who uses this computer” or “Only for me”
4. Now, select the **CurrentWare Components** that you want to install. For first time installation, click next. The install wizard will automatically select the CurrentWare Console and Server to be installed on your computer.
5. Select the **Solutions** that you want to install.
6. Type in the computer name (or IP address) of your CurrentWare Server. For first time installation, click next. The install wizard will automatically type in your Computer name.
7. The Installer will now proceed to install the CurrentWare Server, Console and the solution(s) on your computer.

1.4 Installing the CurrentWare Clients

Follow the instructions below to install the CurrentWare clients on the computers you want to manage. After a successful installation of the CurrentWare Clients, they will connect to your CurrentWare Server and automatically show up on your CurrentWare Console.

Before you begin your installation:

- Installation of all components must be done with an admin user account.
- To successfully deploy the CurrentWare Client using the **Remote Client Install utility**, please temporarily disable the Windows Firewall on the client computers and disable Windows Simple File Sharing.

There are four ways to deploy the CurrentWare Clients to your workstations.

1. **Local CurrentWare Client Install:** run the *cwClient.exe* file on all the computers you want to manage.
2. **Remote Client Install:** use the built-in *Remote Client Install* tool on the CurrentWare Console to push the CurrentWare Client install to the computers.
3. **Deploy the CurrentWare Client by Command Line:** create a batch file that will install the CurrentWare Client. Run the batch file through *Active Directory* or *Login Script*.
4. **Deploy the CurrentWare Client with a Third-Party Software Delivery Tools:** use third-party software to deploy the *cwClient.exe* file.

1.4.1 Local CurrentWare Client Install

This is the most standard method of installing the CurrentWare Client. Run the *cwClient.exe* file on each computer you want to manage.

The *cwClient.exe* file can be found on the computer that you have installed the CurrentWare Server. This set up file is stored under:

CurrentWare Client Setup File:

C:\Program Files\CurrentWare\cwClient\cwClient.exe

When you run the *cwClient.exe* on your managed computers, you will need to fill in the following information.

1. Computer Name or IP Address of the CurrentWare Server

Put in the Computer Name or IP address of the CurrentWare Server that you want the client to connect to. Ensure that the managed workstations can establish connections to the CurrentWare Server.

2. CurrentWare Client Password (Optional)

The CurrentWare Client password is used to configure the CurrentWare Client settings. If you do not put in a custom CurrentWare Client password, then the default password is “Admin” (without the quote; case sensitive).

Upon the completion of your CurrentWare Client installation, it will automatically connect to your CurrentWare Console.

1.4.2 Remote Client Install

Before you begin your installation:

- Disable UAC (User Account Control) and Windows Firewall on the client computers


CurrentWare Clients can be remotely installed from the Console. The remote installer can be found on the console under the menu **Install > Remote Client Install**.

1. Browse for the path of the CurrentWare Client setup file, cwClient.exe, on your computer. By default this file is located in the following folder on the server computer:

C:\Program Files\CurrentWare\cwClient\cwClient.exe

2. Enter the **Computer name or IP address** of the CurrentWare Server.
3. (Optional): Change the **CurrentWare Client password**.
4. Select the option to enable or disable **reboot** after the installation (the recommended option is to enable reboot).
5. Select the computers you want to install the CurrentWare Client on:
 - a. You can enter the IP address manually, or

- b. Click on the Search button to allow CurrentWare to look for the computers on your network, or
 - c. Import from a text file that contains a list of your computers' names or IP addresses.
6. Enter the username and password of an account that has administrative rights to the computers you are installing to
 - a. If you are a domain admin, put in the username in the format of **Domain\Administrator**
7. The CurrentWare Client will now be deployed to the designated computers.



The screenshot shows the 'Remote Client Install' window. It has a title bar with the text 'Remote Client Install'. Below the title bar is a header section with a green icon and the text 'Remote Client Install' and 'Deployment of the CurrentWare Client to the computers on your network'. The main area is divided into four sections: 'Installer Path' with a text box for the path to 'cwClient.exe' and 'Browse'/'Save' buttons; 'CurrentWare Server Settings' with a text box for the server name; 'CurrentWare Client Settings' with a checkbox for changing the password and two text boxes for the new password and confirm password; and 'Reboot Option' with a checkbox for rebooting after installation and a 'Reboot Delay' spinner set to 0 minutes. At the bottom, there is a 'Note' about disabling Firewall and UAC, and 'Next'/'Cancel' buttons.

The First screen of the Remote Client Install Window

If you are encountering the following error messages during the remote client installation, visit this page for help:

<http://www.currentware.com/faqs/remote-client-install/>

1.4.3 Deploy CurrentWare Client by Command Line

The CurrentWare client file can be deployed through a single command line. Below is a list of switches you can along with the command line to deploy the CurrentWare client with the configurations of your choice.

```
e:\cwClient.exe USERPARAMS="-p Admin -ds 192.168.1.100 -rp test -  
sp test" /qn /l e:\install.log /norestart
```

Switches:

-p	Required parameter (password is Admin)
-ds	CurrentWare Server IP address or Computer name
-rp	New Password (Optional)
-sp	Confirm Password (Optional)
/qn	Quiet Install
/l	Create a log file during the install. Specify the location and name of the log file.

In the above example, the network drive is assigned with the letter e:\. The CurrentWare Client set up file is stored on the network drive and the install log file will be created on the network drive after the installation.

1.4.4 Deploy CurrentWare Client with a Third-Party Software Delivery Tool or Active Directory

The CurrentWare Client is packaged as an .exe file and a .msi file. You can find the .msi file as a separate download link from our download page. You can use your company's system deployment tools to deploy the CurrentWare client to your workstations.

Deploy by customizing the cwClient.msi file

You can take the existing cwClient.msi file and customize it with the proper CurrentWare Server Computer name and other parameters before you deploy the file.

Use a MSI editor (for example, the Orca MSI editor) and modify the following table within the cwClient.exe file:

Table	Property	Value
Property	USERPARAMS	"-p Admin -ds 192.168.1.100"

Change the IP address in the value field to the IP address of your CurrentWare Server.

Deploy the .msi file using a Software Delivery Tool or through Active Directory.


1.5 Upgrading the CurrentWare Clients

There are two ways to upgrade the CurrentWare clients in version 4 – Automatic upgrade or Manual upgrade.

1.5.1 Automatic Upgrade of the CurrentWare Clients

The client upgrade process can be automated when you upgrade any version of the CurrentWare client to the latest version.

1. On the CurrentWare Console, go to **Install > Auto Upgrade Clients**
2. Click on the “**Automatically upgrade the CurrentWare Clients on your network...**” checkbox and the CurrentWare Server will push the update to the clients.



The Client upgrade is automatic when this option is enabled.

1.5.2 Manual Upgrade of the CurrentWare Clients

The client upgrade method can be done manually by running the cwClient.exe file on each computer that has a CurrentWare client installed.

1.6 Standalone Installation

Standalone: Installing the CurrentWare Server, Console and Client on the same computer.

1.6.1 Installing the CurrentWare Console, Server and Solution

1. Run the **CurrentWare.exe** setup file
2. Accept the terms in the License Agreement
3. Select the Security Solutions you want to install.
 - a. AccessPatrol: Block USB and external devices
 - b. BrowseControl: Web Filter and Application Blocking
 - c. BrowseReporter: Internet Activity Tracking
 - d. enPowerManager: Remote Power Management
4. The Installer will proceed to install the CurrentWare Server, Console and Solutions onto your computer

1.6.2 Installing the CurrentWare Client

1. Run the **cwClient.exe** setup file
2. When prompted for the CurrentWare Server, put in the word **loopback**. This will make the Client connect to itself
3. Finish the installation

1.6.3 Password Protect the CurrentWare Console


1. Launch the CurrentWare Console
2. Go to Tools > Operators
3. Click on Add and add an operator with administrator role
4. Once an administrator has been added, check the option "Enable Password Security".
5. The next time you launch the CurrentWare Console, it will ask you to enter the operator name and password.

2.0 CurrentWare Console Overview

The CurrentWare Console is the manager that the administrators will use to control the managed workstations.

The CurrentWare Console contains the following functions.

- **Client and Group Management**
- **Redirect Clients**
- **Client Settings**
- **Operators**
- **Import Users**
- **Options**
- **Log Out**



The CurrentWare Console

2.1 Client and Group Management

In computer mode, a connected client is represented by a blue computer icon, while an unconnected client is represented by a grey computer icon. In user mode, an active user is represented by a green user icon, while an inactive user is represented by an orange user icon. For ease of management, the workstations and users can be organized into groups.

Create a New Group

To create a new group, from the menu, select **File > Add New Group**.

Or, right click on the computer pane in the CurrentWare console and select **Add New Group**.

Rename a Group

To rename a group, from the menu, select **File > Rename**

Or, right click on the computer pane in the CurrentWare console and select **Rename**.

Delete a Group

To delete a group, from the menu, select **File > Delete**

Or, right click on the computer pane in the CurrentWare console and select **Delete**.

Move Computers/Users

On the CurrentWare Console, organization of the computers, users and groups can be accomplished by dragging and dropping the selected computer/user into the group. To facilitate the organization of a large number of computers, users or groups, you can use the **Move Computers/Users** function.


On the CurrentWare Console menu, select **File > Move Computer/Users**. The left hand side contains the source folder and the right hand side contains the destination folder. Select the computer(s) you want to move from the source folder, and then select the destination folder. Click on the >> button to move the computers.

2.2 Redirect Clients

Redirect Clients is usually used when there are more than one CurrentWare Servers installed on your network. It is used to connect the CurrentWare Clients from another CurrentWare Server to the current CurrentWare server. Essentially, the redirect clients tool, transfers the CurrentWare Clients from one server to another.

Scenario: I need to transfer all of my CurrentWare Clients from my old server to the new server.

1. On the new CurrentWare Server, launch the CurrentWare Console and access the menu **Tools > Redirect Clients**.
2. Enter the CurrentWare Client password. The default password is Admin
3. Select Redirect All CurrentWare Clients.
4. Enable the option Redirect connected Client(s)
5. Click on OK
6. After a brief moment, the CurrentWare Clients will start connecting to the new Server.



Redirect CurrentWare Clients that are connected to one CurrentWare Server
to another CurrentWare Server

2.3 Client Settings


The CurrentWare Client settings can be modified in the CurrentWare Console under **Tools > Client Settings**. You can also right click on a group to find the Client Settings.

Change Password

Put in the new CurrentWare Client password to replace the existing CurrentWare Client password. You will need to use the CurrentWare client password if you want to change the client settings, such as IP address or computer name of the CurrentWare Server or the port that the client use to connect to the CurrentWare Server. By default the case sensitive Client password is **Admin**.

General


- **Run at Windows Startup:** toggle the option to allow the CurrentWare client service to start every time the workstation boots up.
- **Show in System Tray:** toggle the option to display the CurrentWare icon in the system tray. When this option is enabled, the administrator can double click on the icon, put in the password, to access the CurrentWare Client configuration window.
- **Block admin users from stopping the client:** toggle the option to prevent the users of the workstation to stop the CurrentWare Client service or end the CurrentWare Client process.



CurrentWare Client Settings

Recovery

- The recovery option is for the property of the CurrentWare Client. By default, the option is set to “Restart the Service”. If the CurrentWare Client service was stopped by Windows or another software, the default action would be for the Client to restart itself so it can continue to operate. It is best practice to leave this option as “Restart the Service”.




CurrentWare Client Settings

2.4 Troubleshooting

The troubleshooting option allows administrator to perform troubleshooting tasks to resolve errors that are related to the CurrentWare Client.

Client Restart Schedule

Restarting the CurrentWare Client will resolve unexpected issues that can occur on the CurrentWare Client. This option will help the administrator restart the CurrentWare Client automatically during scheduled time.



Use the Client Restart Schedule to automatically restart the CurrentWare Clients

Viewing Log files

You can use the CurrentWare Console to remotely connect to a client computer to open the CurrentWare Client log files. The following CurrentWare Client log files are available to view remotely:

- **CurrentWare Client Log**
- **Upload Log**
- **Category Log**

CurrentWare Client Log

The CurrentWare Client log indicates the status of the Client. This log file can help identify connection issues and version conflicts.

Upload Log

The upload log records the data, tracked by BrowseReporter, which is uploaded to the CurrentWare Server. This log file can help identify issues with BrowseReporter data upload.

Category Log

The category log records the communication between the CurrentWare Client and the Category Filtering Server used by BrowseControl. If the Category Filtering restriction is not working properly, use this log to identify if the client is connected to the server.

Advanced Logs

Use the CurrentWare advanced log to troubleshoot specific issues that you are having with CurrentWare

- CWSEmail.log
- CWSAPEmail.log
- CWSBRAAlertEmail.log
- CWUserActivity.log
- Advanced client and port connection logs (CltCommand.log, TSTLog8991.log, TSTLog8992.log)

NOTE: Enable advanced logs may cause your system to slow down. After collecting the log files for the technical support team, remember to disable the logging.

2.5 Operators

Operators are used in the CurrentWare Console to assign console permissions to different users. The Operators utility is available on the CurrentWare Console under **Tools > Operators**. There are two types of operators in CurrentWare Console: Administrator and User.

- **Administrator type** has complete control over every computer, group and the solution's functionalities.
- **User type** has limitations defined by the administrator. These limitations include the solution's functionalities and group accesses.

Password Protect the Console

In order to password protect the console, operator accounts need to be created.


Creating an Operator:

1. Launch the CurrentWare Console.
2. On the menu select **Tools > Operators**.
3. Click on the **Add** button.
4. Fill in the name, password and description.
5. Select a role for this operator. While the **Administrator** role has access to all the features of CurrentWare, the **User** role only has the limited access to the solution's functionalities.
6. Click **OK** to create a new operator.

Enable Password Protected CurrentWare Console

1. Create an operator with the step above.
2. Check the option **Enable Password Security**.
3. Log out of the CurrentWare Console.

4. The next time you log into the CurrentWare Console, you will be prompted for a username and password.



Operators

Administrator(s) can add, remove and manage operators here. [Import Active Directory Users as Operators](#)

Manage Operators

Operator	Description
admin	

☐ Enable Password Security
☐ Enable Stricter Password Policies for the Operator.

Operator Permissions Add Remove

Add Operators

Operator: Manager

Password: *****

Confirm Password: *****

Role: ☐ Administrator ☒ User

Description: Manager account with limited access

Update Changes Clear All Add Operator OK

[Help](#)


Administrators have unlimited control. Users have limited controls

2.6 Import Users

The Import users function will import your existing Windows users from your Active Directory domain into the CurrentWare Console.

1. In order to import users, your CurrentWare Console must be in User Mode. Click on the tab called "User Mode" below the toolbar on the left hand side to activate User Mode.
2. Click on **Tools > Import Users**
3. Select to Import from **Active Directory** or from a **Text File**
4. Enter the **Domain administrator** credential (Domain name, user name and password) and click on the Import Users button.
5. A list of your Active Directory Users will be populated in the window.

6. Select specific users you want to add to the CurrentWare Console or click on the checkbox **Select All Users**.
7. Click **Add Users** to add the selected users to the Console.




Import Windows Users from Active Directory

NOTE: When you import users from Active Directory to the CurrentWare Console as operators, the operator name will be the same as the username on active directory. However, the passwords cannot be retrieved directly from the Microsoft Active Directory for security purposes.

The new password for each operator is the username in lowercases. For example, if your Active Directory username is John, your CurrentWare operator password will be john.

2.7 Database Backup Scheduler

The Database Backup Scheduler automatically archives the CurrentWare database (CWNPF.B.CWD) at a scheduled time.




Automatically back up your database at a scheduled time

The archived database is stored under \Program Files\CurrentWare\cwServer\Archive\

You can use the CurrentWare Server Manager to restore an archived database.

2.8 Auto Delete URL Scheduler

Automatically delete Internet history from your database. A smaller database will improve the performance of the CurrentWare Console and reduce the time it takes to generate reports.



In this example, data older than 90 days will be deleted automatically every day at 12:30 PM

Only Keep URLs for: Select the number of days you want to keep your Internet data. The Auto Delete URL scheduler will automatically delete any data that are older than the day that you selected.

Start Time: The scheduler will be executed at this time. During the data cleanup, the Console may close briefly (depending on your database size, the time it takes for the cleanup will vary). After the cleanup is completed, you can resume using the CurrentWare Console.

The CurrentWare Server must be turned on at the Start Time for the cleanup process to happen.


2.9 Options

Details of the Console port and newly connected client management are available on the CurrentWare Console under **Tools > Options**

General

Add new Computers to the group: define the group that a new computer will automatically be assigned to once it connects to the CurrentWare Server for the first time.


Add new Users to the group: define the group that a new user will automatically be assigned to once it is populated to the CurrentWare Server for the first time.



Connection


CurrentWare Server: the computer name or the IP address of the CurrentWare Server that the CurrentWare Console is connected to.

Console Port: The port that CurrentWare Console uses to connect to the CurrentWare Server. The default Console port is 8990.




2.10 Server Settings

Use the Server Settings to change the CurrentWare Server service start up type and recovery mode.



Service Startup Type

Toggle the option “Automatic (Delayed Start)” to change the CurrentWare Server service start up type. Enable this option if your CurrentWare Server service is not starting up automatically during system boot up.



Recovery

The CurrentWare Server service is set to “Restart the Service” if it runs into any failures. This will prevent the CurrentWare Server service from stopping unexpectedly.

2.11 Log Out


Log Out can be used to re-log into the Console with a different user name and password. This feature can be found under the menu **File → Logout**.

3.0 Overview of AccessPatrol Functions

AccessPatrol is an endpoint security tool that allows an administrator to control the device access of your network.

An overview of the AccessPatrol functions includes:

- **Device Blocking**
- **Device Scheduler**
- **Allowed List**
- **Device Reports**
- **Email Reports**



AccessPatrol Solution Features

4.0 Controlling Device Access

AccessPatrol is a device security tool. It allows administrators to control the access of external devices of the users on the network. Below are the main features of AccessPatrol on the CurrentWare Console.

- **Access Permissions**
- **Device Scheduler**
- **Allowed List**

4.1 Access Permissions

AccessPatrol allow the administrator to control the device access privileges for a group of clients or an individual computer.

Full Access: the computer with this access permission can read and write to the specified external devices that are connected to the computer.

Read Only: the computer with this access permission can only read the information from the specified external device that is connected to the computer. The user will not be able to copy any information to the specified external device. This option is only available to storage devices.

No Access: the computer with this access permission cannot read or write to the specified external devices that are connected to the computer.

In the CurrentWare console, groups do not inherit settings from their parent groups. The groups stores the CurrentWare settings independently.

Here is a list of devices that are supported by AccessPatrol:

Storage Devices:

- USB (Removable disk, iPod)
- CD/DVD
- Floppy
- Tape
- External Hard Drive
- FireWire
- SD Card
- MM Card

Communication Ports:

- Serial
- Parallel

Wireless Devices:

- Bluetooth
- Infrared
- Wi-Fi

Other:

- Imaging Devices (Digital camera, Webcam)
- Portable Devices (iPhone, Mobiles)
- Sound Cards

Blocking External Devices on your Network

1. Click on a group or a computer.
2. From the AccessPatrol tab, select **Device Blocking**.
3. Select the device you want to control on the left hand pane.
4. Assign the access permission on the right hand pane.
5. You can block the access permission for all devices by selecting **All Devices** and assign **No access** to it.
6. The devices that are blocked will be listed in the CurrentWare Console under the column **Devices Blocked**.

Read Only Permission: allows the user to read the file but cannot make changes to it. The user will not have the ability to create new files on the controlled devices. Read Only permission is available for storage devices only.

Note for Bluetooth Device blocking: in order to block some Bluetooth devices and its associated services, a reboot may be required on the client's computer.

4.2 Device Scheduler

The device scheduler allows the administrator to assign when the device permissions will be enforced by assigning the start time and stop time for particular devices on the network. Only storage devices are available for the device scheduler.

This is a Group specific setting. Groups can be assigned to three levels of device accesses:

Full Access: the computer with this access permission can read and write to the specified external devices that are connected to the computer.

Read Only: the computer with this access permission can only read the information from the specified external device that is connected to the computer. The user will not be able to copy any information to the specified external device. This option is only available to storage devices.

No Access: the computer with this access permission cannot read or write to the specified external devices that are connected to the computer.

Creating a Device Schedule


1. Highlight the group you want to assign a scheduler to and select **Device Scheduler** under the AccessPatrol tab on the right hand side of the CurrentWare Console.
2. Click on the **Add** button to create a new schedule.
3. Select the **Device type**.
4. Select the **access permission**.
5. Select the **Schedule type**.

6. Select the **Schedule reoccurrence**: Daily, Weekly or Monthly
7. Select the **Schedule Start and Stop Times**.
8. Click on the **Add Schedule** button to create the Device Schedule.

- Up to 20 different device schedules can be set per Group.

9. Click on **Enable Scheduler**

10. Click on **Apply to Clients**



The screenshot shows the 'Device Scheduler' window with the title bar 'Device Scheduler' and a close button. The window contains a header section with a clock icon and the text 'Device Scheduler Daily and Weekly Device Schedules'. Below this is a label 'Device Schedule for Group: Computers'. A table lists device schedules with columns: Device, Block Type, Schedule Type, Start Time, Stop Time, and Days. The first row shows 'Storage Devices' with 'No Access' block type, 'Daily' schedule type, '9:00 AM' start time, and '5:00 PM' stop time. Below the table are 'Add', 'Edit', and 'Remove' buttons. The 'Add Device' section has a dropdown menu set to 'Storage Devices' and three radio buttons for 'Full Access', 'Read Only', and 'No Access' (which is selected). The 'Add Schedule' section has a dropdown menu set to 'Daily', 'Start Time' and 'Stop Time' fields both set to '8:44 PM', and an 'Add Schedule' button. A text box below contains instructions: 'For Daily schedule please select Device, Block type, Schedule type, Start Time, Stop Time and press the button "Add Schedule". For Weekly schedule select the weekdays also.' At the bottom are buttons for 'Help', 'Enable Scheduler', 'Clear', 'OK', 'Cancel', and 'Apply To Clients'.

Device	Block Type	Schedule Type	Start Time	Stop Time	Days
Storage Devices	No Access	Daily	9:00 AM	5:00 PM	

The Device Scheduler sets the time for the device access to go on and off


4.3 Allowed List

Administrators can utilize the Allowed List to specify devices that will have permanent access on the network.

By adding a device to the Allowed List, any user on the network will be able to access it even if the device permission is set to No Access.

The allowed list is folder specific. It applies to any computers that are in the specified folder.

The following devices are supported by the allowed list: *USB and External Hard drive.*



The devices listed on the Allowed list have permanent access by the users.

Adding a device to the Allowed list

1. A device must be physically connected to a computer where the CurrentWare client is installed at one point in time.
2. Click on a group and select **Allowed List** under the AccessPatrol tab
3. Click on **Add from Available Devices**
4. Check the device you want to allow permanently.
5. Click on **Add to Allowed List**
6. Click Ok.
7. Ensure the "**Enable Allowed list**" option is checked.
8. The selected devices will be added to the Allowed list

5.0 Device Reports

The AccessPatrol reporting utility addresses an organization's security compliance of mobile and storage devices.

It serves as an effective tool for analyzing removable device usage and policy enforcement. Effectively identify employees that frequently abuse the endpoint device policies. Through the intuitive reporting tool, generate comprehensive reports highlighting device usage by computer or by user.

5.1 Device Report Options

In the device report option, you can select the types of device access report that you would like to generate. You can also define the computer and the reporting period for which the report data will reflect on.

5.1.1 Reporting Type

The AccessPatrol reports are clear and easy to understand, ranging from executive level summaries to drill down detailed reports for administrators. The reports include:

- **All Devices Accessed**
- **Allowed Devices**
- **Blocked Devices**
- **Allowed vs. Denied Access**
- **Top N Active Machines**
- **USB File Transfer History***

***Note:** On the USB File Transfer History report, you may occasionally see a special character in the filename being replaced by a question mark. This is an indication that the special character is not supported by the character encoding of our database.


5.1.2 Select Mode

Select the computers or users to generate a device report on. You can select an individual computer, multiple computers and a group of computers. The same selection applies for the users.

5.1.3 Reporting Period

Select the time and date period for the report. The reporting period options are as follow:

- All
- Today
- Yesterday
- Last 7 Days
- Last Month
- Custom Range: day and time range.



The image shows a Windows-style dialog box titled "Device Reports". It contains several sections for configuring report generation. At the top, there's a header with the "Device Reports" logo and the instruction "Device Reports - Select the parameters for generating reports." Below this, a section labeled "Enable Device Reporting for Group: Computers" has a checked checkbox for "Enable Device Reporting". The "Report Type" section features a dropdown menu set to "All Devices Accessed" and a text field showing "All Devices Accessed.". Below that, there's a "Return the top" field with the value "10", a "Machines" label, and a "Sort By" dropdown. The "Select the PCs or Users" section has two radio buttons, "PC" (selected) and "User", and a "PCs/Users" button. The "Reporting Period" section includes radio buttons for "All" (selected), "Today", "Yesterday", "Last 7 days", "Last Month", and "Custom Range", followed by an ellipsis button. At the bottom, there are three buttons: "Delete Device History", "Run Report", and "Close".

Device Reports

Device Reports - Select the parameters for generating reports.

Enable Device Reporting for Group: Computers ☒ Enable Device Reporting

Report Type

All Devices Accessed All Devices Accessed.

Return the top 10 Machines Sort By

Select the PCs or Users

Select PCs and Users for report generation.

☒ PC ☐ User PCs/Users

Reporting Period

☒ All ☐ Today ☐ Yesterday ☐ Last 7 days ☐ Last Month ☐ Custom Range ...

Delete Device History Run Report Close

Device Reports Options

6.0 Email Reports


Through the Email Reports feature, the AccessPatrol reports can automatically be generated and emailed to the administrator periodically. This eliminates having to rely on the manual process of creating reports.

To access Email Reports, under the AccessPatrol tab, click on **Email Reports**.

How to create a schedule for e-mail reports:

Note: You must have your email settings configured and a report profile created before creating an email report schedule.

1. Under the AccessPatrol tab on the right hand side of the console, select **Email Reports**.
2. Click on the **Create Schedule** button
3. Define the **email address** of the recipient of the reports.
4. Select a **Report profile** to generate a report of your choice. A report profile is created in the Report Options menu item.
5. Define the **schedule type (daily or weekly)** of the email report.
6. Define the delivery **time** of the email report.
7. The Internet report will be sent in a PDF format.



The screenshot shows the 'Email Reports' window with the 'Email Reports' tab selected. The 'Assign schedule(s) for Emailing reports' section contains a table with the following data:

Email Address	Report Profile	Format	Time	Days
info@currentware.com	test	PDF	5:35 PM	

Below the table are buttons for 'Create Schedule', 'Delete', and 'Edit'. The 'Assign schedule(s) for Emailing reports' section also includes a form with the following fields:

- Email reports to: info@currentware.com
- Report profile: Daily Report (dropdown menu)
- Report format: PDF (dropdown menu)
- Schedule: Daily (dropdown menu)
- Time: 5:00 PM (time picker)
- Buttons: Add Schedule, Clear


At the bottom of the window, there is a note: 'To Email Reports on a regular basis, create a schedule, include the recipient(s) Email address(s), select a Report Profile and the time to send the Email.' and buttons for 'OK', 'Cancel', and 'Apply'.

6.1 Email Settings

Under the Email Settings tab, enter the email configuration that is required to successfully send the reports to the administrator.

How to Configure your Email Settings

1. Enter the appropriate email Information, including the **name**, **email address** and the **password** for your email address.
2. Define the **outgoing mail server** that your email account uses to send email. The default SMTP port that AccessPatrol uses to send email is port 25.
3. Enable **My SMTP server requires authentication** if your email server requires the authentication.
4. You can also use web email services, such as Gmail/ Hotmail/ Yahoo mail, to generate email notifications. These web email services usually require mail server authentication.
5. To test the validity of the email account information, click on the **Test Email Account** button to ensure that the reports will be emailed successfully.
6. Click on the Apply button



The screenshot shows the 'Email Reports' window with the 'Email Settings' tab selected. The window title is 'Email Reports' and the subtitle is 'Email Reports - To create report profile'. The 'Email Settings' tab is active, showing the following fields and options:


- Email Information**
 - Set up the Email account to send reports from:
 - Name: CurrentWare
 - Email Address: info@currentware.com
 - Password: [masked]
 - Confirm Password: [masked]
- Mail Attachment Encoding**
 - Encoding: None
- Outgoing Mail Server Configuration**
 - Outgoing mail server: smtp.currentware.com
 - SMTP Port: 587
 - ☒ My SMTP server requires authentication
 - ☒ Use same settings as my Email information
 - ☐ Log on using
 - Account Name: [empty]
 - Password: [empty]
 - ☒ Log on using Secure Password Authentication

At the bottom right of the form is a 'Test Email Account' button. At the bottom of the window are 'OK', 'Cancel', and 'Apply' buttons.

7.0 AccessPatrol Client Settings

When the CurrentWare Server becomes unavailable, you can retain the access permission on the computer on your network.

Under the AccessPatrol Client Setting, ensure that you have enabled the option called **Enable Device Blocking**.



Enable Device Blocking will continue to control device access when the CurrentWare Server is unavailable.


8.0 CurrentWare Server Manager

The CurrentWare Server Manager is used to manage the administrative tasks of the CurrentWare Server. To access the Server Manager, click on the **Start Menu > Programs > CurrentWare > CurrentWare Server Manager**

8.1 Changing the CurrentWare Client and Console Port

Changes to the Client and Console ports may be required to establish the connections between the CurrentWare server, clients and consoles. For example, if you are using a program that is already utilizing the ports that CurrentWare uses, then you will need to change the ports. Otherwise, please do not modify the Client and Console ports.


The default client port is 8991 and the default console port is 8990.



CurrentWare Server Manager

8.2 Stopping the CurrentWare Server Service

To stop the CurrentWare Server, under the Service tab, click on the button “Stop CurrentWare Server”



8.3 Compress the CurrentWare Database

It is recommended that database compression be performed on a regular basis.

To compress your CurrentWare database:

1. Make sure you have closed the **CurrentWare** Console.
2. Go to the Start menu > Programs > CurrentWare > CurrentWare Server Manager
3. Under the **Compress** tab, click on the **browse** button and search for your CurrentWare database. By default, the database is located under **C:\Program Files\CurrentWare\cwServer\CWNPFB.CWD** .
4. Click on the **Compress** button to begin compressing your database.

8.4 Archive and Restore the CurrentWare Database

In order to maintain optimal database performance, it is recommended that the CurrentWare database be archived on a regular basis. Archiving the CurrentWare database will create a copy of your existing database. However, all tracking data from the existing live database will be deleted.

Note: archiving will create a copy of the current database. After the archiving process is completed, the Internet tracking data for BrowseReporter will be deleted. All Computer and User data will be maintained but the corresponding monitoring data will be removed.

To Archive your CurrentWare Database:

1. Under the **Archive and Restore** tab, click on the **Archive** button (Fig. 21).
2. A copy of your database will be created under **C:\ Program Files\CurrentWare\cwServer\Archive**

Restoring the database will put your current database back to the state it was prior to archiving. The current database will be replaced with the archived database. It is advised that you archive your current database before restoring to a previous database, should you need to retrieve the original data.

Restoring an Archived Database:

1. Under the **Archive and Restore** tab, select the database that you want to restore from the drop-down menu
2. Click on the **Restore** button to begin the process of restoring your archived database.

9.0 Licensing

CurrentWare Solutions are licensed on a per-computer basis for client management.

The evaluation copy of BrowseControl is functional on a maximum of 10 computers for 14 days.

9.1 Register your Permanent License key

After you have purchased BrowseControl, BrowseReporter, enPowerManager or AccessPatrol from CurrentWare, you will receive an email from our licensing department containing your license key information, which includes the following fields:

1. **Organization's Name**
2. **Number of Licenses**
3. **License key**

To register your license key, follow the steps below

1. Launch the CurrentWare Console
2. Go to **Help > Licensing**
3. From the Solutions drop down box, select the **Solution**
4. Copy your **Organization's name, number of licenses and Activation Code** from the licensing email sent to you
5. Click on the **Register** Button
6. Your CurrentWare Console has now been registered.
7. Click on **Next** to manage the computers you want to apply the license keys to.


9.2 License Management

The License Computers console allows the administrator to select the computers to assign the CurrentWare license to. Depending on the installed status of your CurrentWare clients, the licensing process can be automatic or manual.

Managing your CurrentWare Licenses

You will need to manage your CurrentWare Licenses if you have applied your license key before installing your CurrentWare Clients.

1. After you install your CurrentWare Clients, launch your CurrentWare Console
2. Go to **Help > Licensing**
3. Fill in the fields for the Organization name, solution, mode of license, number of licenses and license key
4. Click **next**
5. Now the **License Computers** window will appear. This is where you assign your licenses to your computers. Click on the checkbox to assign a license key to your computer



Manage your CurrentWare Licenses

10.0 Uninstall CurrentWare Server, Console and Solutions

10.1 Uninstalling the CurrentWare Solutions

1. Run the CurrentWare.exe Setup file.
2. Click on "Modify".
3. Click Next until you reach the window where you can select the solutions
4. Uncheck the solutions that you want to uninstall.

10.2 Uninstalling the CurrentWare Server and Console

The CurrentWare Console and Server can be removed from the Control Panel.

1. Before you uninstall the CurrentWare Server and Console
2. Go to Start Menu and select Control Panel
3. Under Programs, Select Uninstall a Program.
4. Uninstall **CurrentWare**

11.0 Uninstall CurrentWare Client


The CurrentWare Client can be uninstalled by two different methods:

- **Uninstall CurrentWare Client from the Console**
- **Uninstall CurrentWare Client on the workstation by command line**
- **Uninstall CurrentWare Client on the workstation from the Client Configuration Window**

11.1 Uninstall CurrentWare Client from the Console

Follow the steps below to uninstall the CurrentWare Client remotely from the CurrentWare Console.

1. Launch the CurrentWare Console
2. Right click on the computer or the group of computers that you want to uninstall, select **Client Service > Uninstall**
3. The client will proceed to uninstall
4. A reboot will be prompted. It is recommended to restart the computer.



11.2 Uninstall CurrentWare Client on the workstation by command line

Follow the steps below to uninstall the CurrentWare Client locally on the workstation by running a command line.

You need to have your CurrentWare Client password in order to uninstall the CurrentWare Client by Command line.

On your CurrentWare Client computer, go to start menu > run > type in the following (for Windows 7, go to the run command box):

For 32-bit Windows PC

C:\Windows\System32\Cwclient.exe -p Admin -u

For 64-bit Windows PC

C:\Windows\SysWOW64\Cwclient.exe -p Admin -u

The word “Admin” in the command is the password field. Admin is the default CurrentWare Client password. If you changed the CurrentWare Client password during the installation, please replace Admin with your CurrentWare Client password.

11.3 Uninstall CurrentWare Client on the workstation from the Client Configuration Window

Follow the steps below to uninstall the CurrentWare Client locally on the workstation from the CurrentWare client configuration Window.

To bring up the CurrentWare client configuration Window, go to C:\Windows\System32 (for 32-bit computers) or C:\Windows\SysWOW64 (for 32-bit computers).

Look for the cwagent.exe file and double click on it.

When prompted for the CurrentWare Client password, type it in (Admin is the default CurrentWare Client password. If you changed the CurrentWare Client password during the installation, please replace Admin with your CurrentWare Client password).

In the CurrentWare Client Configuration Window, click on the General Settings tab. Click on the Uninstall button to uninstall the CurrentWare client from your workstation.

12.0 Technical Support

For technical support of CurrentWare, please contact us at info@currentware.com.

13.0 Contacts

USA

CurrentWare (a division of Codework Inc.)

1623, Military Rd #556, Niagara Falls, NY 14304-1745, United States of America

Tel: 613-368-4300

Fax: 866-929-9808

Email: info@currentware.com

CANADA

CurrentWare (a division of Codework Inc.)

55 Hawktree Ridge, Ottawa, K2J 5N7, Canada

Tel: 613-368-4300

Fax: 866-929-9808

Email: info@currentware.com

EUROPE

CurrentWare (a division of Codework Inc.)

55 Hawktree Ridge, Ottawa, K2J 5N7, Canada

Tel: 613-368-4300

Fax: 866-929-9808

Email: info@currentware.com

ASIA

Codework Solutions Pvt Ltd,

'Thapasya', Infopark, Kakkanad, Kochi, Kerala, India – 682030

Tel: +91-484-4055678

Fax: +91-484-4061003

Email: info@codework.com

OTHER COUNTRIES

Please email info@currentware.com for the name of a local reseller in your country.