

MusicShuffleSync

The shareware(\$5) to make it possible to use your PDA or your MP3 USB Player(must support USB mass-storage-class) like iPodShuffle.

This program shuffles music files in your PC and copy them to SD Card or MP3 USB Player recognised as a removal disk.

****Note****

Since the author of this site is not a native English speaker, the following sentences may be mis-interpreted.

If you find inexcusable incorrect expression , please let me know.

[Overview]

With this program , you can use your PDA or MP3 USB Player as if it were an iPodShuffle.

You don't have to mind the limitation of SD Card free space.

You can listen to different music files from those you listened yesterday.

This program chooses music files at random from your PC not to duplicate with files on a SD Card or MP3 USB Player recognised as a removal disk (Hereinafter calld "device").

Then the program deletes files on the device.

And then the proram copies the choosen music files into the device until there is no vacant free space on the device

or all the music files are copied.

Finally the program shuts down Windows or stands-by Windows if you want.

You don't have to wait for the finish of the synchronization.

You have to just start the synchronization and go to bed. PC automatically turns itself off.

By next morning , everything is done.

[What's New]

01/03/2005 Version 1.00 released.

[Environment]

OS : Windows 2000 , XP


Needed hardware : USB Card reader for a SD Card , if you want to use a SD Card.

[How to use]

1-3 show you how to install and begin use.

4-6 show you an ordinary operation

1. Download the zip file of MusicShuffleSync.
2. Unzip downloaded MusicShuffleSync.zip file, you will find 'MusicShuffleSync.exe'.
3. Copy the exe fille to anywhere you want.
4. Run the copied MusicShuffleSync.exe.
(No installation is necessary for MusicShuffleSync to run.)
5. Following screen will appear.



6. Only the first time you use the program , you have to set some settings.The settings are saved.

At the next time you don't have to set those values.

1. Specify the source folder on your PC by clicking "...". Mp3 and wma files in the source folder and in the sub folders of the source folders are copied into the device.
2. Specify the destination folder on the device (SD Card or MP3 USB Player) by clicking "...".
3. If you want some files not to be copied , you can specify those path using wild card(*?#). Matching rules are subject to 'Like' operator of VB and Office VBA. If you have sufficient knowledge of VB , you can use also character class '['. And you can use '/' as a delimiter to specify multiple path.
4. Choose 'Action before copying files.'
5. Choose 'Action when files are completely copied.'

7. You can create a shortcut on your desktop or under 'Start->Program' by clicking 'Tool' menu on the top of the screen.

[How To Purchase]

The software is a shareware. You can try it for 20days. To use after the period , you have to purchase

a license key code. To purchase a key code , follow the instructions below.

- 1) Run MusicShuffleSync.exe.
- 2) Click 'Purchase'.
- 3) Click 'Purchase' - 'Open the website to purchase a license'.
- 4) You will be led to the author's site and then to the Handango website.
- 5) After the payment , you will receive the key code via E-Mail within 48 hours.
- 6) Click 'Purchase' - 'Type the license code'.
- 7) A text box will appear. Please type the key code into the box by pasting them from the E-Mail.

[WebSite]

http://homepage3.nifty.com/ppc_soft/pc2ppctools/MusicShuffleSync