Relevos 6.0

Quick Start Guide

Relevos 6.0 looks different from previous versions, so we created this guide to help you minimize the learning curve and configure the basic functions of the software.

Get the Status
To check if the computers are ready to run Relevos, press this button. A status will show, with any errors if applicable.

Add a Group
From the GROUPS tab, choose Create a Group. Or, right-click on the tree-view and choose Add a Group

Add a Computer
From the COMPUTERS tab, choose Add Computers, or right-click on the tree-view and choose Add a Computer.

Remote Install
Check the target servers and choose this option to install the Relevos Client to them.

Repair if necessary
If any computers have an issue, you can have Relevos attempt to fix them. Some issues like a remote firewall, cannot be fixed by the Relevos Console.

WMSoftware

continued...

Relevos 6.0

Configure CPU Throttling

CPU Throttling is one of the main features of Relevos. It patented processing enables more capacity on the server and eliminates excessive process CPU utilization without slowing users down.

First, click the CPU tab
The CPU tab contains all of the functions related to controlling CPU utilization. After clicking on the CPU tab, click on the Throttling icon.

Next, select/check servers
Put checkmarks in front of servers that will receive the settings below. Highlight a server if you want to use its settings as a starting point.

Then, turn on Throttling
Turn on the Throttling setting, and adjust the maximum CPU% for each user process. A good starting point is 33%.

Lastly, save settings
Click here to save the settigns to only the checked servers. This same process is used throughout Relevos for sending settings for the chosen option. or full Replication, choose it from the Computers tab.

Advanced
You can choose specific processes or users here.

WMSoftware

Relevos 6.0

Configure Memory Optimizing

Memory Optimizing enables more programs to run within the memory limits of the server. Allocated-but-unused memory is freed but still made available to the program consuming the excessive memory.

First, click the Memory tab
The Memory tab contains all of the functions related to controlling process memory. After clicking on it, click on the Memory Optimize icon.

Next, select/check servers
Put checkmarks in front of servers that will receive the settings below. Highlight a server if you want to use its settings as a starting point.

Then, turn on Memory Optimize
Turn on the Memory setting, and adjust the minimum memory limit used for each user process.

Lastly, save settings
Click here to save the settigns to only the checked servers. This same process is used throughout Relevos for sending settings for the chosen option. For full Replication, choose it from the Computers tab.

Advanced
You can choose specific processes or users here.

WMSoftware

Relevos 6.0

Configure Memory Tracking

Memory Tracking gives administrators a dynamic notification and resolution to user processes that consume excessive memory.

First, click the Memory tab
The Memory tab contains all of the functions related to controlling process memory. After clicking on it, click on the Track icon.

Next, select/check servers
Put checkmarks in front of servers that will receive the settings below. Highlight a server if you want to use its settings as a starting point.

Then, turn on Memory Track
Check the main checkbox to turn on Memory Tracking. A good starting value is 256MB.

Lastly, save settings
Click here to save the settigns to only the checked servers. This same process is used throughout Relevos for sending settings for the chosen option. For full Replication, choose it from the Computers tab.

WMSoftware

Relevos 6.0

Configure Notifications (Email)

Relevos can send notifications to designated emails for the events it tracks.

First, click the Config tab

The Configuration tab contains settings that aren't CPU or Memory-related. For this Quick Start setup,click on the Email icon.

Next, select/check servers

Put checkmarks in front of servers that will receive the settings below. Highlight a server if you want to use its settings as a starting point.

Then, turn on Email Notification

Check the main checkbox to turn on Email Notification, then fill in the fields as appropriate.

Finally, save settings

Click here to save the settigns to only the checked servers. This same process is used throughout Relevos for sending settings for the chosen option. For full Replication, choose it from the Computers tab.

WMSoftware

Relevos 6.0

About

"Good software makes the complex appear simple"

Relevos prevents any user or process from slowing down or bringing a server down.

Relevos throttles CPU and Memory of processes on terminal servers. It works within VMs, on bare metal servers, and with Citrix, ProPalms, and standard terminal server/Remote Desktop Services. It increases user capacity, increases performance, and eliminates user delays by ensuring no user or process can use the CPU at the expense of others. It does this using patented software technology.

Trust what companies worldwide already know: when you need to control the CPU and Memory user processes consume with professional software reliably and affordably, choose Relevos.

Requirements

Relevos requires Remote Desktop Services / Terminal Services.
Relevos runs on Windows Server 2003, 2008, 2008 R2, and 2012.

Relevos uses 35MB RAM and 20MB of disk space.

WMSoftware

Helpful links

Product information

www.wmsoftware.com/relevos

Support

www.wmsoftware.com/support
support@wmsoftware.com
+1 330.558.0501

How to buy

Get a free quote

www.wmsoftware.com/quote

Purchase Online

www.wmsoftware.com/relevos/buynow
sales@wmsoftware.com
+1 330.558.0501
Quantity discounts are available

Purchase using a WM Softwaer Reseller

www.wmsoftware.com/reseller