
Pic Mantra 1.9



User Manual

Copyright ©2004

MantraGroup Inc.
All Rights Reserved.

www.mantragroup.com



Copyright © 2004, MantraGroup Inc., All rights reserved.

Legal Notice

***** Please read this Legal Notice section completely before you use the Application *****

This document contains information proprietary to MantraGroup Inc. No part of this documentation may be reproduced or transmitted in any form or by any means or used to make any derivative work (such as translation, transformation or adaptation) without express written consent from MantraGroup Inc. Any Failure to do so may result in legal action taken by MantraGroup Inc.

License Agreement:

By using this Software or any part of it, you are agreeing to be bound by the terms of this Agreement. If you do not agree to the terms of this Agreement, do not install and use this Software.

About Documentation:

MantraGroup Inc. reserves the right to revise this documentation and to make changes in content from time to time without obligation on the part of MantraGroup Inc. to provide notification of such revision or changes. MantraGroup Inc. has put all the efforts to make the documentation free of errors and is accurate to the best of its knowledge. However, MantraGroup Inc. and its partners who supplied this software make no warranties that the documentation is 100% free of errors. We make no warranties, terms or conditions, express or implied, either in fact or by operation of law. In no event shall MantraGroup Inc. be held liable for any damages arising from the use of this "Pic Mantra" Software.



Pic Mantra Version 1.9

This user manual is designed for the version 1.9 of Pic Mantra.

Pic Mantra Trial

Free 10-day trial version of Pic Mantra is available from MantraGroup Inc. website (www.mantragroup.com) and selected partner web sites. All the features and the functionality in the product can be accessed in the trial period. Registration is required to access the product features after the trial period. If you do not wish to keep the software after trial period, you are required to delete the software from your handheld device.

To register your copy of "Pic Mantra", purchase the product key at www.mantragroup.com or any of its partner websites. To expedite the registration process, you may use the online registration form provided at www.mantragroup.com and obtain the installation key instantaneously.

"Pic Mantra" Standard Edition

You will have the access to all the product features for unlimited time after you buy the product. Also, you will be eligible to receive periodic updates and new product features. Please specify your email at www.mantragroup.com to receive information about the updates and free bug fixes.

Getting Started with "Pic Mantra"

System Requirements

- Palm OS® 4.0 or higher.
- 270K of free memory

Introduction

Pic Mantra is a native JPG and BMP photo viewer for the Palm OS® devices. Pic Mantra will decode all non progressive JPG and BMP images in the internal memory and the external expansion card (Memory Card, Memory Stick etc.).

Pic Mantra includes fast thumbnail view (caching), beam, send pictures to other devices or other applications such as SnapperMail®, rename, delete, add custom note and multiple zooms.


Pic Mantra is capable of receiving JPG and BMP pictures beamed to the Palm and will display the picture automatically after the beam.

User Interface

There are 3 different modes for file listing.



Modes



File List Mode - Displays all the pictures in the list view.



Thumbnail Mode - Displays all the pictures in thumbnails.



Detail View - Displays all the details of pictures.

1) **File List Mode:** File name, type and size are shown.




Diagram 5: FileList Mode



2) **Thumbnail Mode:** Thumbnails and names are shown.




Diagram 6: Thumbnail Mode

3) **Detail Mode:** Thumbnail, name, size, dimensions, location and the category are shown.




Diagram 7: Detail Mode



Pic Mantra Settings




Diagram 2: Pic Mantra Settings

☒ Cache the Thumbnails

For faster response, Pic Mantra stores thumbnails in the internal memory. Each thumbnail takes 5k of store (18k if higher density levels are allowed).

Delete the Cache

Deletes the thumbnail cache. This option is useful if there is shortage of space in memory. Disabling the cache will not delete the thumbnail cache. So, this option will be used to delete the cache.

Make Pic Mantra Default to receive:

☒ JPEG

☒ BMP

Pic Mantra will register as the default viewer for the selected type. When the picture is beamed or sent to the Palm, Pic Mantra will receive the picture and display it automatically.

Pic Mantra Menu





Diagram 3: Pic Mantra Menus

- **View** - The image is decoded.



- **Delete** - Deletes the selected image.



- **Beam** - Beams the selected image to other devices if it is in internal memory. To beam a file on external card, copy it to internal memory and then beam.
- **Send** - Sends the selected image through libraries like SMS and Bluetooth. By default, SMS and Bluetooth both register themselves here, but there can be other libraries available. The list of available libraries is displayed. The user can pick the transfer mode.
- **Info** - Displays the information about the selected image. The user can change the category of the image and add custom notes for the image.
- **Rename** - Renames the selected image file.
- **Copy to External Memory / Copy to Internal Memory** - Only one of the two options is displayed when a file is selected. The file in internal memory can be copied to external memory and vice versa.

Picture	Options
	Settings
	Register PicMantra
	About PicMantra

- **Settings** - Opens the Settings screen.
- **Register Pic Mantra** - If not registered, opens registration form. Pic Mantra can be registered.
- **About Pic Mantra** - Displays the about screen.



Popup Menu




Diagram 4: Pic Mantra Popup Menu

Tap and hold on a file item to get the popup menu.

The last option 'Copy to External Card' is displayed if the selected file is in internal memory. If the file is in external memory, the option is replaced with 'Copy to Internal Memory'.

Toolbar



- View the selected image.

Same as 'View' option in Pic Mantra Menu and Popup Menu.



- Displays the information about the selected image.



- Refreshes the displayed list.

Picture Information



Diagram 8: Information screen



The Picture Information screen gives information about the picture such as name, size, dimensions and location (Internal or External). You can add a note to the picture. The category of the picture can be changed by tapping on appropriate category as displayed in the above diagram.

Viewing Pictures




Diagram 9: View screen

View Screen Toolbar




Diagram 10: View screen Toolbar

Zooming is between 1/3x and 8x.  (Back) will display the previous screen.

Beam Save Screen

Save Beamed File
Name of the Beamed File:
gaudi.jpg
Category: ▼ Unfiled
Location: ▼ Internal



Diagram 11: Beamed File Save Screen

The beamed file can be saved in internal or external memory. The category of the beamed file can be selected.

Tapping on Save or Discard will save or discard the file and then return to the previous screen.

